I UPLOAD MY LOGS TO

THE ARRL

LOGBOOK

OF THE WORLD

How To Configure
N3FJP AC Log
To Upload Logs To
Logbook of The World

If you need assistance with AC Log please visit the N3FJP web pages
http://www.N3FJP.com/

or the users group forum.

- N3FJP AC Log is a popular logging program.

- One of the features of AC Log is the ability to upload QSOs directly to your Logbook of The World account.

- This tutorial will enable you to enter the required information to take advantage of this feature.

- N3FJP AC Log is **NOT** an ARRL program therefore we can not offer any support for this software package.

- If you contact ARRL about this software you will be directed to the N3FJP website.

1. Open the N3FJP ACLog program.
2. Select the LoTW button.

Logbook of the World Manager

Status: Ready

Sign and Upload

User Name:

N1ZQ

Login Password:

PASSWORD

Station Location:

EX: N3FJP Home

Selected Contacts from Main Form

All Contacts not Uploaded

Entire Log

Edit   Add

Extra line breaks in this message were removed.

From: lotw-admin@arrl.org   Sent: Wed 8/25/2010 12:11 PM
To:
Cc:
Subject: LoTW Certificate

Attachments: N1ZQ.tq6 (34 KB)

Here is your LoTW certificate for N1ZQ
You may be able to install this certificate by double- clicking on the attachment icon. If that isn't possible or doesn't work, save the attached file to disk and then use the TQSLCert program's "Load Certificate File" menu command to install this certificate into your system.

NOTE: If the attachment failed to arrive with this message, you can just log on to the Web site noted below using the provided username and password and download the certificate file directly.

Records submitted using this certificate can be accessed on the Web using:
username: n1zq
password:
at https://www.arrl.org/lotw/
NOTE! This is NOT the same password the TQSL program asks for when you're signing a file!

On the left side of the form enter the LoTW account username and password.

The information for USERNAME and PASSWORD are in the body of the e-mail which contained your TQ6 file.

Please note that this is NOT the postcard password or the private key password that you created when requesting a certificate.

Now enter the TQSL station location.

Note that the selected station location name is shown in gray at the lower portion of the TQSL form. <u>The station location name is case sensitive</u>.

In this example the station location is N1ZQ Hartford.
The station location is ***NOT*** N1ZQ-N1ZQ Hartford.

The station location must match exactly as you entered it when you created the station location in TQSL. (see www.arrl.org/instructions for information on how to create a station location in TQSL.)

Please note that the Add and Edit buttons will open the TQSL program to add a new location or edit an existing location.

These buttons will not add or edit anything in the N3FJP program.

Enter your call sign in the box "Own Call."

Verify that the path to Trusted QSL is correct.

The default path is C:\program files\TrustedQSL.

For Windows 7 and Vista 64 the default path is
C:\program files (x86)\TrustedQSL.

Verify the LoTW server settings.

These server settings are the same for all users.

LoTW upload URL

https://p1k.arrl.org/lotwuser/upload?login=

LoTW download URL

https://p1k.arrl.org/lotwuser/lotwreport.adi?login=

Upload your log.

Use the "All contacts not uploaded" button as this eliminates uploading QSOs already uploaded to the LoTW server.

Download, Import or "Sync" your QSOs

Support

ARRL does not support N3FJP AC Log or any third party software.

If you need assistance with AC Log please visit the N3FJP web pages http://www.N3FJP.com or the users group forum.

DO NOT contact LoTW help or ARRL with questions about AC Log. You will only be directed to the above sources.